


PRINTING FROM PHOTOSHOP



STEP 1


- Go to **FILE, PRINT**

STEP 2 (Photoshop Print Settings window)

- Set Printer: **Epson Stylus Pro 3800 or 3880**
(Depending on your computer station)
- Click **“Print Settings”** button
(new print window should appear)

STEP 3 (In new print window)

- Set Printer:
Epson Stylus Pro 3800 or 3880
(Depending on your computer station)
- **Paper Size:** Determined by you




STEP 4 (In new print window)

From print window on **MATTE COMPUTER...**

- choose **Printer Settings** from center drop down menu

- **Media type:** Ultra Premium Presentation Paper Matte
- **Print Mode:** AccuPhoto HD2
- **Check box for 16 Bit Output**
- **Color Mode:** Off (No Color Management)
- **Output Resolution:** SuperFine – 1440 dpi
- **Uncheck last 3 boxes**
- Click **SAVE**
- Click **PRINT** from large print window



STEP 4 (In new print window)

From print window on **LUSTER COMPUTER...**

- choose **Print Settings** from center drop down menu

- **Media type:** Ultra Premium Photo Paper Luster
- **Color:** Color
- **Check box for 16 Bit Output**
- **Color Settings:** Off (No Color Management)
- **Print Quality:** SuperFine – 1440 dpi
- **Uncheck last 3 boxes**
- Click **SAVE**
- Click **PRINT** from large print window

PRINTING FROM PHOTOSHOP



STEP 5

- Click to open **COLOR MANAGEMENT** tab
- Color Handling:** Photoshop Manages Colors
- Select Printer Profile based on computer station**

Matte Computer:
(Adrian 216)



Matte Computer:
(Adrian 217)




Photo Black Computer:
(Adrian 216)





Photo Black Computer:
(Adrian 217)



- Rendering Intent:**
Perceptual or Relative Colorimetric
(If Relative Colorimetric check box for "Black point")



STEP 6

- Click to open **POSITION AND SIZE** tab
- Position:** Add checkmark to Center
- Scaled Print Size:** 100%

STEP 7

- Hit PRINT**
(Make sure paper is in printer)